

CHAPTER-1

Enterprise Structure:

1) Define company:-

A company is a group or trade mark, it can be maximum of 6 digit number it can be alpha & numeric.

Transaction code - /NOX15
Press enter
Click on **new entries**
Company **ala8**
Company name **ala8India**
City **Bangalore**
Country **IN** (India) (Press F4)
Language **EN** (English) (Press F4)
Currency **INR** (Press F4)
Enter save and enter

2) Define company code:-

A company code is organization unit under which we create **profit & Loss and Balance Sheet**.

A company code can be maximum 4 digit number it can be alpha numeric under one company we can create N# of company codes.

Transaction code - /NOX02
Press enter
Click on New Entries
Company code **AlA8**
Company name **ALA8India**
City **Bangalore**
Country **IN** (India) (Press F4)
Launage **EN** (India) (Press F4)
Currency **INR**
Enter once & save

Title **Company**
Name **ala8India**
Street/house # **Jayanagar** **123456**
Postal code / City **580062** **Bangalore**
Country **IN**
Enter twice

3) **Assign company code to company:-**

Transaction code - /NOX16
Click on position
Company code ALA8
Press enter
Company ALA8
Press enter
Enter save & enter

4) **Define business area:-**

Business area is organization unit under which we create **dummy Profit & loss statement**.

Transaction code - /NOX03
Press enter
Click on New entries

<u>Business area</u>	<u>Description</u>
ALA8	ALA8 business area

Enter save enter

5) **Define chart of account:-**

List of all the GL account will be stored under **chart of account**.

There are 3 types of chart of account:

- 1) Operating chart account i.e **day to day actives**.
- 2) Country chart account that is for **legal specific requirement of thatcountry**.
- 3) Group chart of account that is for **consolidation purpose**.

The **length of GL account number can be 1 to 10**.

For one company code we can assign maximum **2 charts of account operating & country**.

Transaction code - /NOB13
Press enter
Click on New entries
Chart of account ALA8
Description ALA8
Maintain launage EN (English)

Length of GL account # 6

Enter save & enter

6) **Assign chart of account to company code:-**

Transaction code - /NOB62

Press enter

Click on position

Company code ALA8

Press enter

Company code company name chart account city

ALA8

ALA8

Enter save enter

7) **Define fiscal year variant :-**

Fiscal year variant is a financial year it can be maximum 2 digit number.

The standard Fiscal year variants are:

K4 (Jan to Dec)

V3 (April to march)

V6 (July to June)

V9 (Oct to Sep)

Note:- In SAP 1year = 16 months i.e. 12+4=16 12 is a year & 4 is special periods.

The purposes of special period are audit, Tax & adjustment.

Transaction code - /NOB29

Click on New entries

<u>FV</u>	<u>Description</u>	<u>year-dependent</u>	<u>calendar year</u>	<u># of posting</u>
8L	Jan-Dec		Should tick	12

Of special period

4

Enter save enter

8) **Assign company code to Fiscal year variant:-**

Transaction code - /NOB37

Click on position

Transaction code - /NOBB0
 Press enter
 Click on new entries

Variant	Name
ALA8	ALA8 Posting period variant

Enter save enter

12) Assign company code to posting period variant :-

Transaction code - /NOBBP
 Press enter
 Click on position

Company	Variant
ALA8	ALA8

Enter save enter

13) Define open and close position period:-

To create open and close posting period we required posting period variant we required this entry is we important for creating month end activity.

Transaction code - /NOB52
 Press enter
 Click on new entries

Variant	A	From Period	Year	To Period	Year
ALA8	+	1	2015	12	2015

Save

14) Define tolerance group for GL account:-

Transaction code - /NOBA0
 Click on new entries
 Company code ALA8
 Tolerances group ----- ALA8 TOLERANCE

Enter save enter

15) Define finances (FI) tolerance group for user:-

Transaction code - /NOBA4
Press enter
Click on new entries
Company code ALA8

Upper limits for posting procedure

Amount per documents 999999999999 (It should be 13 #)
Amount per open item account item 9999999999 (It should be 11 #)
Cash discount per line item 99%

Enter save and enter
Tolerance means either discount or upper limit.

Open item:-Non cleared item are called open item.

16) Credit control area:-

It is a credit limit to the customer's one credit control can be assign to n # of company code.

Transaction code - /NOB45
Press enter
Click on new entries
Credit control area ALA8
Currency INR
Credit limit 9999999999
Tick all company code
Save

17) Assign company code to credit control area:-

Transaction code - /NOB38
Click on position
Company code ALA8

CCAR
ALA8

Enter save enter

18) Define field status variant:-

Field status variant can't be created it has to copied.

To create field status group we required field status variant. Field status group are very important to create GL master.

Field status group are identifies whether it required, optional, display entry

Transaction code - /NOBC4

- 1) Select full row 0001 click on copy AS (F6)
- 2) Remove 0001 & put ALA8 then press enter
- 3) Click on copy all then press enter
Select full row ALA8 double click on field status group.
- 4) Double click on G001 double click on General data, text should be optional rest all should be suppress
- 5) Then save

19) Assign company code to field status variant:-

Transaction code - /NOBC5

Click on position

Company code ALA8

Press enter

Field status variant ALA8

20) View company code data OR Global data:-

Transaction code - /NOBY6

Click on position

Company code ALA8

Double click on ALA8

Tick on negative posting permitted

Cash management activated

Enter save enter

Note:-

SL No...	Charters	T-code
1	Company	/nox15
2	Company Code	/nox02
3	Assign company code to company	/nox16
4	Business area	/nox03
5	Chart of Account	/nob13
6	Assign Chart of account to Company Code	/nob62
7	Physical year Variant	/nob29
8	Assign Company Code to Fiscal Variant	/nob37
9	Retain Earning	/nob53
10	GL account groups	/nobd4
11	Posting Period Variant	/nobb0
12	Assign Company code to posting period variant	/nobbp
13	Open & close position period	/nob52
14	Tolerance group for GL account	/noba0
15	Finance tolerance group for user	/noba4
16	Credit control area	/nob45
17	Assign company code to credit control area	/nob38
18	Field status variant	/nabc4
19	Assign company code to field status variant	/nabc5
20	View Company code data or global data	/noby6